

# ManageEngine ADAudit Plus

## Using MS SQL Server as Backend

1. [Pre-requisites](#)
2. [Execute "ChangeDB.bat" in ADAudit Plus](#)
3. [Points to be noted](#)

## Pre-requisites

1. Ensure the SQL Server Native Client is installed in the computer where ADAudit Plus is running.
2. Copy "bcp.exe" and "bcp.rll" to the "<Installation Folder>\bin" folder., eg., C:\Program Files\ManageEngine\ADAudit Plus\bin
  - a. These files are available in "Command line utilities for SQL Server", please ensure version compatibility while installing [ [download details](#) ]

## Execute "ChangeDB.bat" in ADAudit Plus

1. Now, you need to provide the details about the SQL server to ADAudit Plus by executing the file ChangeDB.bat
2. Navigate to "<ADAudit Plus Installation Folder>/bin" folder and execute "ChangeDB.bat"
3. Select 'Server Type' as SQL Server and enter other values
  - a. **Host Name:** The name or the IP address of the machine where MSSQL server is installed.
  - b. **Port:** The port number in which ADAudit Plus must connect with the database. Default is 1433.
  - c. **MSSQL Server Instances :** The available SQL Server instances are listed here, select the appropriate one.
  - d. **Database Name:** Name of the AdAudit Plus database. Default is "adap". If you want to have a different database name, you may specify here.
  - e. **Authentication:** The way in which you would like to connect to the SQL server.
    - i. **Windows Authentication:** If you are connecting to the SQL server from Windows, you have the option to make use of the Windows Single Sign On facility provided ADAudit Plus service is running with a service account, which has the privilege to connect to SQL server.
    - ii. **SQL Authentication:** Using accounts that are created in SQL Server and are not based on Windows user accounts
    - iii. **Note:** It is recommended to choose the option 'Windows' as the username and password used for authentication are not stored anywhere.
  - f. **User Name and Password:** If you have selected the option "SQL", specify the user name and password with which ADAudit Plus needs to connect to the database.
  - g. The user name and password entered here will be stored in "database\_params.conf" file in ADAudit Plus. So, you need to take care of hardening the host.
  - h. Finally, click "Test Connection" to ensure that the connection settings are proper and then click "Save"

## Download details - Command line utilities for MS SQL Server

SQLServer Version	Command line utilities	Native Client
2005	<a href="#">Download</a>	<a href="#">Download</a>
2008 R2	<a href="#">Download</a>	<a href="#">Download</a>
2012	<a href="#">Download</a>	<a href="#">Download</a>

### Points to be noted

1. "dbcreator" - [Server role](#) is suffice for MS SQL Server operations.
2. If firewall is ON in the MS SQL Server computer, please ensure TCP - 1433 and UDP - 1434 are open.
3. "SQL Browser" service should be running on MS SQL Server.